

Chapter 6

Instabilities of homogeneous, parallel shear flow: the effects of viscosity

To this point, we have investigated shear instability in the simplest possible context: a homogeneous, inviscid fluid. In this chapter and the next, we will restore viscosity and buoyancy to the theory. So here, we imagine a parallel shear flow in a fluid that is homogeneous but has nonzero viscosity.

On a geophysical scale, molecular viscosity is often a minor influence. However, small scale turbulence affects instability in a manner very similar to viscosity. Picture, for example, an ocean current $\sim 100\text{m}$ thick, growing instabilities on a scale of $\sim 1000\text{m}$. The flow is continually scrambled by turbulent eddies on scales of $\sim 1\text{m}$ or less. The small eddies transfer momentum through the flow in a manner similar to molecular collisions, and the effect is often represented using a “turbulent viscosity”, ν_t , which is much larger than the molecular value. In sophisticated models, ν_t is assumed to vary in space and time. As a start, though, one can treat ν_t as a constant, in which case it is mathematically no different from molecular viscosity. Here, the symbol ν can mean either phenomenon.

In the presence of viscosity, the divergence equation is unchanged from (1.6.2):

$$\vec{\nabla} \cdot \vec{u} = 0. \quad (6.0.1)$$

The momentum equation (1.6.5), neglecting buoyancy but retaining viscosity, is

$$\frac{D\vec{u}}{Dt} = -\vec{\nabla}\pi + \nu\nabla^2\vec{u}. \quad (6.0.2)$$

The viscosity term involves fourth derivatives and therefore requires additional boundary conditions. These will be discussed in detail below (section 6.4). For the moment we’ll just observe that, in addition to impermeability ($w = 0$), viscosity requires that fluid at the boundary must move with the boundary, so for a stationary boundary $u = v = 0$.

6.1 Conditions for equilibrium

Consider a parallel shear flow

$$\vec{u} = U(z)\hat{e}^{(x)}.$$

This automatically satisfies the divergence equation. If we now substitute into (6.0.2) we have

$$\frac{\partial \Pi}{\partial x} = \nu \frac{\partial^2 U}{\partial z^2} \quad (6.1.1)$$

$$\frac{\partial \Pi}{\partial y} = \frac{\partial \Pi}{\partial z} = 0 \quad (6.1.2)$$

From (6.1.2) we see that the pressure gradient is arranged so as to balance the force of viscosity acting on the mean flow. We'll call this **frictional equilibrium**. Clearly Π can be at most a function of x .¹ Equation (6.1.1) therefore requires that a function of x equal a function of z , which is possible only if both are constant. A parallel shear flow that is stationary in a viscous fluid must therefore obey

$$\frac{d^2 U}{dz^2} = \text{const.}$$

Therefore U must take one of three forms: (i) a quadratic function of z if the constant is nonzero, (ii) a linear function if the constant is zero, or (iii) zero, which is uninteresting. An immediate consequence of this is that $d^2 U/dz^2$ cannot change sign, i.e., there is no inflection point. In the absence of viscosity, this class of flows would be stable. We now consider two examples.

Plane Poiseuille flow: A parallel flow driven by a constant pressure gradient is a quadratic function. With stationary boundaries at $z = 0$ and $z = H$, U has the form

$$U(z) = 4u_0 \frac{z}{H} \left(1 - \frac{z}{H}\right), \quad (6.1.3)$$

where u_0 is the maximum velocity, found at $z = H/2$ (figure 6.1a). The effect of viscosity is balanced by a constant pressure drop in the x direction.

$$\frac{d\Pi}{dx} = -8\nu \frac{u_0}{H^2}.$$

Incidentally, plane Poiseuille flow has a cylindrical counterpart, the classical engineering problem of flow in a pipe.

Plane Couette flow: If there is no pressure gradient, the velocity profile is a linear function. One way to power a flow in this circumstance is to have one boundary move relative to the other, e.g.

$$U(z) = \frac{u_0 z}{H}.$$

In this case the boundary at $z = H$ moves at speed u_0 and the boundary at $z = 0$ is stationary (figure 6.1b).

6.2 Conditions for quasi-equilibrium: the frozen flow approximation

If the mean flow is *not* in equilibrium, we cannot use our methods of stability analysis, because the normal mode solution (3.3.1) is invalid when the coefficients of the equations are functions of time. So, channeling

¹Compare this with the inviscid case, section 3.2.1, where $\nu = 0$ and therefore Π is uniform.




Figure 6.1: Equilibrium states in a viscous fluid. (a) Plane Poiseuille flow maintained by a uniform pressure gradient. (b) Plane Couette flow driven by a moving upper boundary.

our inner child, we ask, "But can we do it if the mean flow is *almost* in equilibrium?" The answer is yes, we can, if we're very careful.

Suppose that the mean flow is not exactly in equilibrium; it is evolving slowly, perhaps under the action of viscosity. Suppose also that an instability grows on that mean flow very rapidly, so that it reaches large amplitude before the mean flow has time to change very much. We can guess, then, that the evolution of the mean flow will have little effect on the instability. On that basis, we can do the stability analysis with normal modes just as if the mean flow were steady. This is called the **frozen flow approximation**. But, we must check afterward to make sure that the growth rate really is fast enough to justify the approximation.

Suppose that the mean velocity profile $U(z)$ can be characterized by a length scale h and a velocity scale u_0 . Suppose further that it diffuses under the action of viscosity on a time scale T_v . Now assume that there is no pressure gradient to force the flow; it's just diffusing freely:

$$\frac{\partial U}{\partial t} = \nu \frac{\partial^2 U}{\partial z^2}. \quad (6.2.1)$$

We can estimate the terms in this equation as follows:

$$\frac{u_0}{T_v} = \nu \frac{u_0}{h^2},$$

or

$$T_v = \frac{h^2}{\nu}.$$

Now if

$$\sigma T_v \gg 1,$$

then the instability will grow by many factors of e in the time it takes the mean flow to diffuse. Suppose, for example, that the instability is a shear instability, so its growth rate scales like

$$\sigma = \sigma^* \frac{u_0}{h}.$$

Then the condition $\sigma T_v \gg 1$ is equivalent to

$$\sigma^* \gg \frac{\nu}{u_0 h},$$

or

$$\sigma^* \gg \frac{1}{Re}, \quad (6.2.2)$$

where

$$Re = \frac{u_0 h}{\nu} \quad (6.2.3)$$

is the **Reynolds number**. Any solution we obtain that does not satisfy (6.2.2) must be interpreted with great caution.

6.3 The Orr-Sommerfeld equation

We now substitute perturbation forms

$$\vec{u} = U(z)\hat{e}^{(x)} + \varepsilon\vec{u}'; \quad \pi = \Pi(x) + \varepsilon\pi'$$

into the equations of motion (6.0.1) and (6.0.2). The procedure is very similar to the inviscid case which we examined in detail in section 3.2.2; we have only to account for the added term representing viscosity in the momentum equation. Viscosity makes no difference to the divergence condition (3.2.5):

$$\vec{\nabla} \cdot \vec{u}' = 0. \quad (6.3.1)$$

Because there is no nonlinearity in the viscous term, the momentum equation is just (3.2.8) with the extra term:

$$\frac{\partial \vec{u}'}{\partial t} + U(z)\frac{\partial \vec{u}'}{\partial x} + w'\frac{dU}{dz}\hat{e}^{(x)} = -\vec{\nabla}\pi' + \nu\nabla^2\vec{u}'. \quad (6.3.2)$$

To obtain the Helmholtz equation for the pressure, we again take the divergence of the momentum equation. Because the divergence of the added viscosity term is zero by (6.3.1), the result is exactly the same as (3.2.12):

$$\nabla^2\pi = -2U_z\frac{\partial w'}{\partial x}.$$

We now substitute the Helmholtz equation into the Laplacian of the vertical component of (6.3.2). The result is just (3.2.13) with the added viscosity term:

$$\frac{\partial}{\partial t}\nabla^2 w' + U\frac{\partial}{\partial x}\nabla^2 w' - U_{zz}\frac{\partial w'}{\partial x} + \nu\nabla^4 w' = 0. \quad (6.3.3)$$

Substituting the normal mode form (3.3.1) now gives the **Orr-Sommerfeld equation**:

$$\sigma\nabla^2\hat{w} = -ikU\nabla^2\hat{w} + ikU_{zz}\hat{w} + \nu\nabla^4\hat{w}, \quad (6.3.4)$$

where

$$\nabla^2 = \frac{d^2}{dz^2} - \tilde{k}^2; \quad \tilde{k}^2 = k^2 + \ell^2.$$

This may also be written in terms of the phase speed, $c = i\sigma/k$:

$$(U - c)\nabla^2\hat{w} = U_{zz}\hat{w} - \frac{\nu}{k}\nabla^4\hat{w}. \quad (6.3.5)$$

In the special case $\nu = 0$, this is equivalent to the Rayleigh equation (3.3.6). We can see immediately that the viscous case differs from the inviscid case in a very important way: the flow can be stable in the sense that the perturbed flow returns to its original equilibrium state (compare with section 3.5). Because one term in (6.3.5) has an imaginary coefficient, it is not true that a solution $[c, \hat{w}]$ is accompanied by a conjugate solution $[c^*, \hat{w}^*]$. It is therefore possible (and in fact common) for all modes to have negative growth rates.

6.4 Boundary conditions for viscous fluid

We will always assume impermeable boundaries $\hat{w} = 0$ (cf. 3.6.5) above and below the region of interest. But because the Orr-Sommerfeld equation (6.3.4) is fourth-order (it contains fourth derivatives in the viscous term, two more boundary conditions are needed. The correspond to additional assumptions we make about the nature of the boundary. There are two plausible assumptions: rigid and frictionless.

6.4.1 The rigid boundary

This is the most obvious choice. Physically, we know that velocity goes to zero at a boundary, because fluid molecules wind up among the boundary molecules. In the case of a moving boundary, the flow velocity approaches the boundary velocity. Here, we'll assume stationary boundaries, but the generalization to a moving boundary is trivial. So not only is $w' = 0$ at the boundaries, but u' and v' are zero also.

We're not done yet, though. These additional conditions pertain to u' and v' , but we need conditions on w' . We arrange this as follows. Because $u' = 0$ *everywhere* on the boundary, and in particular for all values of x , it also follows that $\partial u' / \partial x = 0$ everywhere in the boundary. Likewise, because $v' = 0$ for all y , $\partial v' / \partial y = 0$. Substituting these results into the divergence condition:

$$\frac{\partial u'}{\partial x} + \frac{\partial v'}{\partial y} + \frac{\partial w'}{\partial z} = 0,$$

When working with normal modes, the condition at a **rigid boundary** is

$$\boxed{\hat{w}_z = 0.} \quad (6.4.1)$$

6.4.2 The frictionless boundary

In most flows, the retarding effect of viscosity is restricted to a thin layer adjacent to the boundary, within which the velocity goes rapidly to zero. This is called the viscous boundary layer. Outside the viscous boundary layer, the velocity changes much more slowly; the fluid slips past as if the boundary were frictionless.

If the region of flow is much larger than the viscous boundary layer, we can pretend that the outer edge of the layer is actually the boundary, and impose the condition that $\partial u' / \partial z = \partial v' / \partial z = 0$ at that location. An equivalent way to state this is that the viscous momentum fluxes $-\nu \partial u' / \partial z$ and $-\nu \partial v' / \partial z$ vanish at the boundary. The boundary may therefore be called “flux-free” or just “free”.

To convert this condition to a condition on w' , we use the derivative of the divergence condition. Because $\vec{\nabla} \cdot \vec{u}' = 0$ everywhere in the flow, its z -derivative is also zero:

$$\frac{\partial}{\partial z} \left(\frac{\partial u'}{\partial x} + \frac{\partial v'}{\partial y} + \frac{\partial w'}{\partial z} \right) = \frac{\partial^2 u'}{\partial x \partial z} + \frac{\partial^2 v'}{\partial y \partial z} + \frac{\partial^2 w'}{\partial z^2} = 0.$$

Now since $\partial u' / \partial z = 0$ for all x , $\partial^2 u' / \partial x \partial z = 0$, and by the same reasoning $\partial^2 v' / \partial y \partial z = 0$, leaving us with $\partial^2 w' / \partial z^2 = 0$. In normal mode form, the condition at a **free** (or frictionless) boundary is

$$\boxed{\hat{w}_{zz} = 0.} \quad (6.4.2)$$

6.5 Matrix solution of the Orr-Sommerfeld equation

Write the Orr-Sommerfeld equation in the form (6.3.4):

$$\sigma \nabla^2 \hat{w} = -\iota k U \nabla^2 \hat{w} + \iota k U_{zz} \hat{w} + \nu \nabla^4 \hat{w},$$

where

$$\nabla^2 = \frac{d^2}{dz^2} - \tilde{k}^2.$$

Possible choices of boundary conditions include

$$\hat{w} = 0; \quad \hat{w}_z = 0 \quad (\text{rigid}) \quad (6.5.1)$$

$$\hat{w} = 0; \quad \hat{w}_{zz} = 0 \quad (\text{free}). \quad (6.5.2)$$

As in the inviscid case, the Laplacian is represented as a matrix \underline{A} :

$$\nabla^2 \rightarrow \underline{A} = \underline{D}^{(2)} - \tilde{k}^2 \underline{I},$$

where $\underline{D}^{(2)}$ is the second derivative matrix incorporating the appropriate boundary conditions (6.5.1 or 6.5.2).

Similarly, the right-hand side of the Orr-Sommerfeld equation is expressed using a second matrix which is just (3.6.2) with the extra viscous term:

$$\underline{B} = -\imath k \vec{U} \cdot \underline{A} + \imath k \vec{U}_{zz} \cdot \underline{I} + \nu (\underline{D}^{(4)} - 2\tilde{k}^2 \underline{D}^{(2)} + \tilde{k}^4 \underline{I}), \quad (6.5.3)$$

where $\underline{D}^{(4)}$ is a fourth derivative matrix incorporating the boundary conditions. With free-free boundary conditions, the fourth derivative matrix turns out to be equivalent to the square of the second derivative matrix (try it!). If either boundary is rigid, though, the fourth derivative matrix must be designed separately via Taylor series expansions as described in sections 1.5.2 and 1.5.3. Left-multiplications are performed as in section 3.6.2. The Orr-Sommerfeld equation now becomes a generalized eigenvalue problem:

$$\sigma \underline{A} \vec{w} = \underline{B} \vec{w}.$$

6.6 Oblique modes

As we discussed in section 3.8, for every oblique mode we can define a corresponding 2D mode. If the oblique mode has wave vector (k, ℓ) , then there is a corresponding 2D mode with wave vector $(\tilde{k}, 0)$ (figure 3.10). The growth rates are σ and $\tilde{\sigma}$, respectively. We found that, in the absence of viscosity, the growth rates are related by $\sigma = \cos \varphi \tilde{\sigma}$, where φ is the angle of obliquity. Here we will see how viscosity affects that relationship.

We begin by writing the Orr-Sommerfeld equation (6.3.4) more explicitly:

$$(\sigma + \imath k U) \left(\frac{d^2}{dz^2} - \tilde{k}^2 \right) \hat{w} = \imath k U_{zz} \hat{w} + \nu \left(\frac{d^2}{dz^2} - \tilde{k}^2 \right)^2 \hat{w} \quad (3D)$$

Suppose we have a solution algorithm for this equation:

$$\sigma = \mathcal{F}(z, U, \nu; k, \ell). \quad (6.6.1)$$

This equation and solution algorithm pertain to any mode, an oblique mode in particular.

For a corresponding 2D mode, having wave vector $(\tilde{k}, 0)$, this would be

$$(\sigma + \imath \tilde{k} U) \left(\frac{d^2}{dz^2} - \tilde{k}^2 \right) \hat{w} = \imath \tilde{k} U_{zz} \hat{w} + \nu \left(\frac{d^2}{dz^2} - \tilde{k}^2 \right)^2 \hat{w}, \quad (2D)$$

with solution algorithm

$$\sigma = \mathcal{F}(z, U, \mathbf{v}; \tilde{k}, 0). \quad (6.6.2)$$

Alternatively, we can start with (3D) and make the Squire transformations $\sigma = \tilde{\sigma} \cos \varphi$ (as we did in the inviscid case; section 3.8), and

$$\mathbf{v} = \tilde{\mathbf{v}} \cos \varphi.$$

Substituting these into (3D) and dividing out the common factor $\cos \varphi$, we have

$$(\tilde{\sigma} + i\tilde{k}U) \left(\frac{d^2}{dz^2} - \tilde{k}^2 \right) \hat{w} = i\tilde{k}U_{zz}\hat{w} + \tilde{\mathbf{v}} \left(\frac{d^2}{dz^2} - \tilde{k}^2 \right)^2 \hat{w}. \quad (\widetilde{3D})$$

The form ($\widetilde{3D}$) is isotropic to the special case (2D):

$$(\widetilde{3D}) \leftrightarrow (2D), \text{ under } \tilde{\sigma} \rightarrow \sigma \text{ and } \tilde{\mathbf{v}} \rightarrow \mathbf{v}.$$

This means that we can use the same solution algorithm as for the 2D case (6.6.2):

$$\tilde{\sigma} = \mathcal{F}(z, U, \tilde{\mathbf{v}}; \tilde{k}, 0),$$

or

$$\sigma = \cos \varphi \times \mathcal{F}\left(z, U, \frac{\mathbf{v}}{\cos \varphi}; \tilde{k}, 0\right).$$

So a general 3D mode, with $\varphi \neq 0$ corresponds to a 2D mode ($\varphi = 0$), with growth rate reduced by the factor $\cos \varphi$ as in the inviscid case, but **the corresponding 2D mode grows on a flow with increased viscosity $\tilde{\mathbf{v}} = \mathbf{v}/\cos \varphi$.**

It is often true that viscosity has the effect of *damping* instability, as we have seen in the convection case (chapter 2). If that is true, the tendency of 2D modes to grow faster than the corresponding 3D modes is increased by this heightened sensitivity to viscosity. However, it is not impossible that viscosity could tend to destabilize a flow. If that were true, and if that viscous destabilization was sufficient to overcome the leading factor $\cos \varphi$, then a 3D mode could grow faster than the corresponding 2D mode.

6.7 Shear scaling and the Reynolds number

Here again is the Orr-Sommerfeld equation (3D):

$$(\sigma + \iota kU) \left(\frac{d^2}{dz^2} - \tilde{k}^2 \right) \hat{w} = \iota kU_{zz}\hat{w} + \mathbf{v} \left(\frac{d^2}{dz^2} - \tilde{k}^2 \right)^2 \hat{w}, \quad (3D)$$

with solution algorithm

$$(\sigma, \hat{w}) = \mathcal{F}(z, U, \mathbf{v}, k, \ell).$$

Note that we have taken an extra step by including the eigenfunction \hat{w} in the output of \mathcal{F} .

For shear scaling, we define a length scale h and a velocity scale u_0 , just as in section 3.7. For example, the familiar hyperbolic tangent shear layer

$$U = u_0 \tanh \frac{z}{h}$$

can be written as

$$U^* = \tanh z^*,$$

where

$$U^* = \frac{U}{u_0}; \quad z^* = \frac{z}{h},$$

(reproducing 3.7.2). Other quantities can be scaled as in (3.7.6), also reproduced here for convenience:

$$\begin{aligned} \sigma &= \sigma^* \frac{u_0}{h} \\ \{k, \ell, \tilde{k}\} &= \{k^*, \ell^*, \tilde{k}^*\} / h \\ \hat{w} &= \hat{w}^* u_0 \\ \frac{d}{dz} &= \frac{1}{h} \frac{d}{dz^*} \quad \Rightarrow \nabla^2 = \frac{1}{h^2} \left(\frac{d^2}{dz^{*2}} - \tilde{k}^{*2} \right). \end{aligned}$$

With these substitutions, the Orr-Sommerfeld equation (3D) can be rewritten as

$$(\sigma^* + ik^*U^*) \left(\frac{d^2}{dz^{*2}} - \tilde{k}^{*2} \right) \hat{w}^* = ik^*U_{z^*z^*}^* \hat{w}^* + \frac{\nu}{hu_0} \left(\frac{d^2}{dz^{*2}} - \tilde{k}^{*2} \right)^2 \hat{w}^*, \quad (3D^*)$$

The scaled viscosity appearing in the second term on the right-hand side is the inverse of the Reynolds number (6.2.3). (3D*) is isomorphic to (3D) and therefore has the same solution algorithm under the shear scalings listed above

$$(\sigma^*, \hat{w}^*) = \mathcal{F}(z^*, U^*, 1/Re, k^*, \ell^*). \quad (6.7.1)$$

6.8 Application: viscous stabilization of a shear layer

Consider a hyperbolic tangent shear layer $U^* = \tanh z^*$ in a viscous fluid. In the limit $Re \rightarrow \infty$, viscosity is negligible and the instability is indistinguishable from that found in an inviscid fluid (section 3.11). As Re is reduced, the effects of viscosity become evident (figure 6.2). The growth rate of the fastest-growing mode decreases, and its wavelength increases. (As in the case of convective instability, larger-scale disturbances are better able to resist viscous damping.) The flow is completely stabilized when $Re = 2.7$. That number should be taken with a large grain of salt, however, since the condition $\sigma^* \gg 1/Re$ is not satisfied.

A useful and valid rule of thumb² that we can extract from this analysis is that viscous effects become important when Re drops below ~ 100 . Suppose, for example, that the shear layer at the base of the ocean mixed layer is 10m thick, and the velocity change across it is 0.1m/s, so that $h = 5\text{m}$ and $u_0 = 0.05\text{m/s}$. In that case, the condition $Re < 100$ is equivalent to $\nu > 2.5 \times 10^{-4}\text{m}^2/\text{s}$. That value is in the normal range for turbulent viscosity at the mixed layer base, and we should therefore expect that shear instability in this regime will be affected significantly by ambient turbulence.

6.9 Application: instabilities of plane Poiseuille flow

Here we use the matrix-based numerical approach to explore the instabilities of plane Poiseuille flow (6.1.3; figure 6.1), which is one of the few shear flows that are truly stationary in a viscous fluid. In shear-scaled

² “It’s more of a guideline than a rule.” Bill Murray in “Ghostbusters”.




Figure 6.2: Stability characteristics of a hyperbolic tangent shear layer $U^* = \tanh z^*$ in a viscous fluid. Frictionless boundaries are placed at $z^* = \pm 5$. (a) Fastest growth rate of shear layer instability versus Re . The red curve indicates $1/Re$. (b) Wavenumber of fastest-growing mode. Asterisks show the inviscid result (e.g. figure 3.12).

terms, the mean flow profile is

$$U^* = 4z^*(1 - z^*). \tag{6.9.1}$$

We begin by setting the spanwise wavenumber ℓ^* to zero and looking at the growth rate as a function of streamwise wavenumber k^* for a range of Reynolds numbers. A distinct region of instability is found (figure 6.3), with maximum growth rate at $Re = 10^5$. This is called the **Tollmein-Schlichting instability**. In this case the fastest-growing mode has $k^* = 1.55$, or wavelength about 4 times the width of the channel.

For $Re > 10^5$, the maximum growth rate increases with decreasing Re , i.e. with increasing viscosity. This is therefore an example of a mode that is destabilized by viscosity. In the absence of viscosity (the limit $Re \rightarrow \infty$), the growth rate is zero.

Contours of the cross-stream velocity perturbation (figure 6.4) show that isolines tilt against the background shear near the boundaries. It is this aspect of the perturbation that allows it to access energy from the mean flow despite the absence of an inflection point.

The fact that the Tollmein-Schlichting mode is destabilized by viscosity raises the possibility that the fastest growing instability may be oblique (on the basis of Squire’s theorem). In figure 6.5, we show a test of this possibility for a value $Re=5 \times 10^5$, well into the region where growth rate increases with increasing viscosity (figure 6.3). The fastest-growing mode is in fact two-dimensional; all oblique modes have lower growth rates.

Test your understanding: Is the criterion $\sigma^* \gg 1/Re$ relevant for plane Poiseuille flow?

6.10 The perturbation kinetic energy budget for parallel shear flow in a viscous, homogeneous fluid

When exploring the inviscid case, we derived the kinetic energy equation in terms of real perturbation variables u', v', \dots , etc., which represent a general disturbance (section 3.9.1). We then applied the result to a normal mode perturbation by integrating quadratic combinations over one wavelength (section 3.11.1). Here we will repeat the derivation with viscous terms included, and we’ll allow for fully three-dimensional modes ($\ell \neq 0$). And, just for variety, we’ll do the math in normal mode form right from the start.

As in the inviscid case, the perturbation equations describing continuity and momentum are given by (6.3.1)

Figure 6.3: Stability characteristics of plane Poiseuille flow (6.9.1). Colors indicate the growth rate versus wavenumber k^* and Reynolds number for 2D modes $\ell^* = 0$. For $Re > 10^5$ (above the red line), the growth rate decreases with increasing Re or, in other words, increases with increasing viscosity. The dashed line pertains to figure 6.5.





Figure 6.4: Vertical velocity perturbation for the Tollmein-Schlichting instability of plane Poiseuille flow. (a) The entire vertical domain. (b) Blowup of the lower region bounded by the dashed line in (a), showing the up-shear phase tilt.




Figure 6.5: Growth rates of oblique modes of plane Poiseuille flow versus scaled wavenumber. $Re = 5 \times 10^5$, indicated figure 6.3 by the dashed line. Growth is maximized in the 2D limit despite the destabilizing role of viscosity.

and (6.3.2). In normal mode form, these can be written as:

$$\iota k \hat{u} + i l \hat{v} = -\hat{w}_z, \quad (6.10.1)$$

$$(\sigma + \iota k U) \hat{u} = -U_z \hat{w} - \iota k \hat{\pi} + \nu \nabla^2 \hat{u} \quad (6.10.2)$$

$$(\sigma + \iota k U) \hat{v} = -i l \hat{\pi} + \nu \nabla^2 \hat{v} \quad (6.10.3)$$

$$(\sigma + \iota k U) \hat{w} = -\hat{\pi}_z + \nu \nabla^2 \hat{w} \quad (6.10.4)$$

where the subscript z indicates the derivative. We now multiply the momentum equations, (6.10.2), (6.10.3) and (6.10.4), by the complex conjugates of the velocity eigenfunctions, \hat{u}^* , \hat{v}^* and \hat{w}^* respectively, and add the results:

$$\underbrace{(\sigma + \iota k U) (|\hat{u}|^2 + |\hat{v}|^2 + |\hat{w}|^2)}_{(1)} = \underbrace{-U_z \hat{u}^* \hat{w}}_{(2)} - \underbrace{\iota k \hat{u}^* \hat{\pi} + i l \hat{v}^* \hat{\pi} - \hat{w}^* \hat{\pi}_z}_{(3)} + \underbrace{\nu (\hat{u}^* \nabla^2 \hat{u} + \hat{v}^* \nabla^2 \hat{v} + \hat{w}^* \nabla^2 \hat{w})}_{(4)}. \quad (6.10.5)$$

Next, we take the real part of each term.

1. The real part of term (1) is $4\sigma_r K$, where

$$K = \frac{|\hat{u}|^2 + |\hat{v}|^2 + |\hat{w}|^2}{4} \quad (6.10.6)$$

is the perturbation kinetic energy.

2. The real part of term (2) is twice the shear production:

$$SP = -\frac{U_z}{2} (\hat{u}^* \hat{w})_r.$$

3. The first two terms of (3) can be written as

$$(-\iota k \hat{u}^* - \iota \ell \hat{v}^*) \hat{\pi}.$$

The sum in parentheses is equal to $(\iota k \hat{u} + \iota \ell \hat{v})^*$, which is equal to $-\hat{w}_z^*$ by (6.10.1). Therefore, (3) can be rewritten as

$$-\hat{w}_z^* \hat{\pi} - \hat{w}^* \hat{\pi}_z = -(\hat{w}^* \hat{\pi})_z.$$

After taking the real part, the quantity in parentheses is twice the energy flux:

$$EF = \frac{(\hat{w}^* \hat{\pi})_r}{2},$$

so that the real part of (3) is $-2EF_z$, or $2FC$.

4. The fourth term is due to viscosity. Here, we'll split that term into two parts which represent distinct physical processes. The three terms multiplied by viscosity all have the same form, which can be rewritten as follows:

$$\begin{aligned} \hat{u}^* \nabla^2 \hat{u} &= \hat{u}^* \hat{u}_{zz} - \tilde{k}^2 \hat{u}^* \hat{u} \\ &= (\hat{u}^* \hat{u}_z)_z - \hat{u}_z^* \hat{u}_z - \tilde{k}^2 \hat{u}^* \hat{u} \\ &= (\hat{u}^* \hat{u}_z)_z - |\hat{u}_z|^2 - \tilde{k}^2 |\hat{u}|^2 \end{aligned}$$

We now take the real part. The only complex term on the right hand side is the first one, and its real part is the derivative of

$$(\hat{u}^* \hat{u}_z)_r = \frac{1}{2} (\hat{u}^* \hat{u}_z + \hat{u} \hat{u}_z^*) = \frac{1}{2} (\hat{u}^* \hat{u})_z = \frac{|\hat{u}|_z^2}{2},$$

so we have

$$(\hat{u}^* \nabla^2 \hat{u})_r = \frac{|\hat{u}|_{zz}^2}{2} - |\hat{u}_z|^2 - \tilde{k}^2 |\hat{u}|^2. \quad (6.10.7)$$

Adding the corresponding terms involving \hat{v} and \hat{w} , we can now assemble term (4):

$$2K_{zz} - |\hat{u}_z|^2 - |\hat{v}_z|^2 - |\hat{w}_z|^2 - 4\tilde{k}^2 K.$$

Collecting all four terms of (6.10.5) and dividing by 2, we have the kinetic energy for normal modes in a viscous shear flow:

$$\boxed{2\sigma_r K = SP - EF_z + \nu K_{zz} - \varepsilon.} \quad (6.10.8)$$

The final term is minus the viscous dissipation rate

$$\boxed{\varepsilon = \frac{\nu}{2} (|\hat{u}_z|^2 + |\hat{v}_z|^2 + |\hat{w}_z|^2 + 4\tilde{k}^2 K).}$$

The new terms we have gained via the addition of viscosity are

- The perturbation kinetic energy (6.10.6) now includes the third velocity term, $|\hat{v}|^2$.
- The term νK_{zz} is the convergence of a kinetic energy flux due to viscosity, $-\nu K_z$.
- The dissipation rate $-\varepsilon$ is negative definite and therefore destroys perturbation kinetic energy (converting it to heat).

None of the viscous processes can *create* perturbation kinetic energy. The viscous flux $-vK_z$, like the pressure-driven flux EF , vanishes at the boundaries (check!) and therefore does not contribute to the net kinetic energy in the domain. The dissipation term $-\varepsilon$ is negative definite, and hence can only reduce the kinetic energy. This is something of a paradox, since viscous flows have instabilities that do not exist in the absence of viscosity, as in the case of the Tollmein-Schlichting instability of the plane Poiseuille flow (figure 6.3). Because viscosity forces the total velocity \vec{u} to go to zero at the boundaries, the perturbation is distorted such that lines of constant w' tilt against the background shear (figure 6.4) and SP is therefore positive as shown in section 3.12.4. In other words, while viscosity does not create perturbation kinetic energy directly, it reconfigures the perturbation so that it can extract kinetic energy from the mean flow despite the absence of an inflection point.

6.11 Summary

- A parallel shear flow in a viscous fluid can be in equilibrium if either
 - the mean shear is uniform, so that U does not diffuse (as in Couette flow), or
 - viscous smoothing is balanced by a pressure gradient in the x -direction (as in Poiseuille flow).
- The frozen flow approximation permits the use of normal modes provided that the instability grows rapidly compared with the time scale of viscous alteration of the mean profile.
- The Orr-Sommerfeld equation is solved numerically in a manner very similar to the Rayleigh equation, but an extra boundary condition (either rigid or frictionless) is needed.
- Except in unusual cases, the fastest-growing mode is 2D.
- The effect of viscosity is expressed by the Reynolds number, Re . Viscosity acts to damp shear instability when Re is less than ~ 100 .
- Viscosity can *create* shear instability - not directly, but by forcing the disturbance to obey the rigid boundary condition and thereby generating positive shear production.